

Sothink Video Encoder Engine for Adobe Flash (Web Control Center) Configuration Instructions for PHP

This instruction is applied to the application program of Sothink Video Encoder Engine for Adobe Flash (Linux Version). After installation of the program, you could go further to configure the built-in Web Control Center for more convenient video conversion and management.

You can either use the built-in Web Control Center in software package to manage, convert and publish video; or use the command-line directly to complete server-side and database configuration; or use other administration program developed by yourself to realize server-side video encoding.

1. Install WAMP
You can use any method to install WAMP installation package.
2. Setup php.ini file after WAMP installation.
upload_max_filesize = 30M ; Maximum allowed size for uploaded files.
post_max_size = 30M ; Maximum size of POST data that PHP will accept.
max_execution_time = 120 ; Maximum execution time of each script, in seconds.
max_input_time = 120 ; Maximum amount of time each script may spend parsing request data.
memory_limit = 120M ; Maximum amount of memory a script may consume (8MB).
3. Install Sothink Video Encoder Engine for Adobe Flash (Web Control Center)
 - ① Copy all the files under the FvecWeb folder to the folder where WAMP scripts are executed;
 - ② Input the URL in the location bar of the web browser to start installation, for example:
http://www.yoursite.com/install; Then please follow the prompts to install Sothink Video Encoder Engine for Adobe Flash (Web Control Center);
 - ③ After installation completed, please delete the install folder manually;
 - ④ Login and now start using Sothink Video Encoder Engine for Adobe Flash (Web Control Center);
4. Assign Permissions
Make sure you have assign permissions for the root directory of the website you have created. Set the permissions to 777 for all the files under the root directory of the website.



Note:

** You can either use the built-in Web Control Center in software package to manage, convert and publish video; or use the command-line directly to complete server-side and database configuration; or use other administration program developed by yourself to realize server-side video encoding.

** If you would like to use Sothink Video Encoder Engine for Adobe Flash command line version only, you may directly copy catalog "upload/fvec" to your server. As for the usage of Sothink Video Encoder Engine for Adobe Flash command line version, please check file "/api/fvec.chm".